

4½" x 4½" x 11½"
 (excluding handle)



FABRIC REQUIREMENTS	
	Fabric A 30165 E ¼ YARD
	Fabric B 30166 R ¾ YARD
	Fabric C 30167 E ¾ YARD
ADDITIONAL SUPPLIES REQUIRED: 1 Pkg. Soft and Stable byAnnie's	



We recommend that you carefully read through all instructions before getting started on your project.

CUTTING DIRECTIONS

Fabric A, cut:

- (1) 5" x WOF strip.
Subcut into (4) 5" squares.

Fabric B, cut:

- (1) 5" x WOF strip.
Subcut into (5) 5" squares for top band and tote bottom and (4) 3" x 5" rectangles for bottom band.
- (1) 4" x WOF strip.
Subcut into (1) 4" x 12" strip for handle.

Fabric C, cut:

- (2) 5" x WOF strips.
Subcut into (1) 5" square for bottom lining and (4) 5" x 12" side lining rectangles.


Soft and Stable, cut:

- (4) 12" x 5" rectangles for sides.
- (1) 5" square for bottom.
- (1) 4" x 12" rectangle for handle.


SEWING INSTRUCTIONS

Use a 1/4" seam allowance for all stitching.

1. Stitch a 3" x 5" **Fabric B** rectangle to a 5" **Fabric A** square to a 5" **Fabric B** square to make a side strip. Press seams away from the **Fabric A** square.
2. Baste a 12" x 5" rectangle Soft and Stable to the wrong side of the side strip.
3. Repeat steps 1 and 2 to complete 4 side strips.
4. Join the 4 side strips along the 12" sides to make an open-ended box, stopping stitching 1/4" from the bottom end of each seam. Press seams open.




5. Baste the Soft and Stable to the 5" **Fabric B** bottom square. With right sides together, stitch the square to the bottom of the box, pivoting at each corner, to complete the tote shell.




6. Repeat steps 4 and 5 with the **Fabric C** lining pieces, leaving a 3" opening on 1 side seam for turning. Turn right side out and press.

7. Baste the 4" x 12" Soft and Stable to the wrong side of the matching size Fabric B handle strip.

8. Fold the handle strip in half along length with right sides together and stitch along the 12" side. Turn right side out and press with seam flat on 1 side to prepare the handle.



9. With right sides together, center the handle on opposite sides of the tote shell; baste to hold.



10. With right sides together, place the lining inside the tote shell, matching seams. Stitch the layers together around the top edge.

11. Turn the tote right side out through the opening left in 1 lining seam. Hand-stitch the opening closed. Tuck the lining inside the tote and poke corners together at the bottom with fingers. Press top edge flat.

12. Topstitch 1/4" around the top edge to complete the tote.

While all possible care has been taken to ensure the accuracy of this pattern, we are not responsible for printing errors or the way in which individual work varies.